

Lesson 2 Target Tracking

1. Working Principle

Recognize the color and process it with Lab color space. Firstly, convert RGB color space to LAB and then perform binaryzation, dilation and erosion and other operations to obtain the outline of the target color. Then frame the contour of the color to complete color recognition.

Then process height of robotic arm after recognition. The coordinates (x,y,z) of center point of image takes as the set value and the currently obtained coordinates are used as input value to update pid.

Then, calculate on the basis the feedback of image position. Finally, the coordinate value will change linearly through the change of the position, so as to achieve the effect of tracking.

The source code of program is located in:

/home/ubuntu/armpi_pro/src/object_tracking/scripts/object_tracking_node.py



```
81 def reset():
82     global target_color
83     global arm_x, arm_y
84
85     with lock:
86         arm_x = Arm_X
87         arm_y = Arm_Y
88         x_pid.clear()
89         y_pid.clear()
90         arm_x_pid.clear()
91         arm_y_pid.clear()
92         off_rgb()
93         target_color = 'None'
94
95     # app initialization call
96 def init():
97     rospy.loginfo("object tracking Init")
98     initMove()
99     reset()
100
101 # image process result callback function
102 def run(msg):
103     global lock
104     global move
105     global arm_x, arm_y
106
107     center_x = msg.center_x
108     center_y = msg.center_y
109     radius = msg.data
```

2. Operation Steps

i It should be case sensitive when entering command and the “Tab” key can be used to complete the keywords.

2.1 Enter Game

1) Turn on ArmPi Pro and connect to the system desktop via No Machine.

2) Click  and select  in pop-up interface to open the terminal.

3) Enter command “`roslaunch object_tracking object_tracking_node.py`” and press “Enter” to run the program of target tracking.

```
ubuntu@ubuntu:~$ roslaunch object_tracking object_tracking_node.py
[DEBUG] [1656589583.407065]: init_node, name[/object_tracking], pid[22602]
[DEBUG] [1656589583.412227]: binding to 0.0.0.0 0
[DEBUG] [1656589583.417123]: bound to 0.0.0.0 33069
[DEBUG] [1656589583.422855]: ... service URL is rosrpc://ubuntu:33069
[DEBUG] [1656589583.427693]: [/object_tracking/get_loggers]: new Service instance
```

4) Do not close the opened terminal and open a new terminal. Then enter command “`rosservice call /object_tracking/enter "{}"`” to enter and press “Enter” to enter this game. After entering, the terminal will print the prompt as the figure shown below:

```
ubuntu@ubuntu:~$ rosservice call /object_tracking/enter "{}"
success: True
message: "enter"
```

2.2 Start image transmission

2.2.1 Start with browser


To avoid consuming too much running memory of Raspberry Pi. It is recommended to use an external browser to open the transmitted image.

1) Select a browser. Take Google Chrome as example.



- 2) Then enter the default IP address “192.168.149.1:8080/” (Note: this IP address is the default IP address for direction connection mode. If it is LAN mode, please enter “Device IP address+: 8080/”. For example, “192.168.149.1:8080/”) If fail to open, you can try it several times or restart camera.

Note: If it is in LAN mode, the method to obtain device IP address can refer to “10.Advanced Lesson”/ 1.Network Configuration Lesson/ LAN Mode Connection.



- 3) Then, click the option shown in the following figure to open the display window of the transmitted image.



/visual_processing/image_result




2.2.2 Start with rqt

- 1) After completing the steps of “2.1 Enter Game” and do not exit the terminal, open a new terminal.
- 2) Enter command “rqt_image_view” and press “Enter” to open rqt.

```
ubuntu@ubuntu:~$ rqt_image_view
```

- 3) Click the red box as the figure shown below, select “/visual_processing/image_result” for the topic of line following and remain other settings unchanged.



Note: After opening image, the topic option must be selected. Otherwise, after starting game, the recognition process can not be displayed normally.

2.3 Start Game

Now, enter the terminal according to the steps in “2.1 Enter Game” and input command “`rosservice call /object_tracking/set_running "data: true"`”. Then if the prompt shown in the following red box appears, which means game has been started successfully.

```
ubuntu@ubuntu:~$ rosservice call /object_tracking/set_running "data: true"
success: True
message: "set_running"
ubuntu@ubuntu:~$
```

After starting the game, select the target color. Take blue as example. Enter command “`rosservice call /color_tracking/set_target "data: 'blue'"`”.

Note: If want to change to green or red, you can fill in green or red in "data: '" (The entered command should be case sensitive).

```
ubuntu@ubuntu:~$ rosservice call /object_tracking/set_target "data: 'blue'"
success: True
message: "set_target"
ubuntu@ubuntu:~$
```

2.4 Stop and Exit

- 1) If want to stop the game, enter command "rosservice call /object_tracking/set_running "data: false"". After stopping, you can refer to the content of "2.3 Start Game" to change other tracking colors.

```
ubuntu@ubuntu:~$ rosservice call /object_tracking/set_running "data: false"
success: True
message: "set_running"
```

- 2) If want to exit the game, enter command "rosservice call /object_tracking/exit {}" to exit.

```
ubuntu@ubuntu:~$ rosservice call /object_tracking/exit "{}"
success: True
message: "exit"
```

- 3) To avoid consume too much running memory of Raspberry Pi, after exiting the game and returning to the terminal of running game programmings, press "Ctrl+C" to exit the program. If fail to exit, please keep trying several times.

```
[INFO] [1656053310.803753]: data: "blue"
[DEBUG] [1656053310.917365]: connecting to ubuntu 38919
[INFO] [1656053337.062093]: stop running object tracking
[DEBUG] [1656053337.102660]: connecting to ubuntu 38919
[INFO] [1656053352.044230]: exit object tracking
[DEBUG] [1656053352.056126]: connecting to ubuntu 38919
[INFO] [1656053352.145915]: 'NoneType' object has no attribute 'cancel'
^C[DEBUG] [1656053365.322010]: connecting to ubuntu 38919
[DEBUG] [1656053365.340156]: TCPServer[37005] shutting down
[INFO] [1656053365.877228]: shutdown
```


Note: Before exiting the game, it will keep running when Raspberry Pi is powered on. To avoid consume too much running memory of Raspberry Pi, you need to exit the game first according to the operation steps above before performing other AI vision games.

- 4) If want to close the image transmission, press “Ctrl+C” to return and open the terminal of rqt. If fail to exit, please keep trying several times.

```
Terminal - ubuntu@ubuntu: ~
File Edit View Terminal Tabs Help
ubuntu@ubuntu:~$ rqt_image_view
libEGL warning: DRI2: failed to authenticate
^Cubuntu@ubuntu:~$
```

3. Project Outcome

After starting game, place the blue block within the detected range of camera. The target color will be framed in rqt tool after recognition. At this time, move the block slowly. Then the robotic arm will rotate to the direction of the block and the car will move to the block.





4. Function Extension


4.1 Add New Recognition Color

Target tracking has three built-in color red, green and blue. In addition to the built-in colors, we can add other recognition colors. For example, add pink as a new recognizable color. The operation steps are as follow:

1) Open the terminal, enter command “python3 lab_config/main.py” and press “Enter” to open the tool for color threshold adjustment. If no transmitted image appears in the pop-up interface, it means the camera fails to connect and needs to be checked whether the wire is connected.




2) After the camera is connected completely, we can see that the right side is real-time transmitted image and the right side is the color to be collected. Then click “Add” in the lower right color to name the new color.




3) Fill in the name of added color and click “Ok”. The color will be updated to “pink” in the color options bar in the lower right corner.








4) Point the camera at the pink object. Then drag the following six slider bars until the pink area becomes white and other areas become black and click "Save" to save data.



5) Find the source code of target tracking and double click to open. Then input the RGB value of pink in source code and save it.



- 6) Open the terminal and enter command “`sudo systemctl restart start_node.service`” to restart the game. (Wait for 1 minute to hear “Di” sound, then the game is restarted successfully)
- 7) Refer to the operation steps from 2.1 Enter game to 2.3 Start game to start color tracking.
- 8) Put pink object in front of the camera then slowly move the object. Arm Pi Pro will move with the pink object.



9) If want to add other colors as new recognizable color, you can refer to the operation steps of “4.1 Add New Color”.

4. Program Parameter Instruction

4.1 Image Process

The source code of image process program is located in:
`/home/ubuntu/armpi_pro/src/visual_processing/scripts/visual_processing_node.py`

```

227 # single color detection
228 def color_detect(img, color):
229     global pub_time
230     global publish_en
231     global color_range_list
232
233     if color == 'None':
234         return img
235
236     msg = Result()
237     area_max = 0
238     area_max_contour = 0
239     img_copy = img.copy()
240     img_h, img_w = img.shape[:2]
241     frame_resize = cv2.resize(img_copy, size_m, interpolation=cv2.INTER_NEAREST)
242     frame_lab = cv2.cvtColor(frame_resize, cv2.COLOR_BGR2LAB) # convert image into LAB space
243
244     if color in color_range_list:
245         color_range = color_range_list[color]
246         frame_mask = cv2.inRange(frame_lab, tuple(color_range['min']), tuple(color_range['max'])) # Bitwise operation
247         # operates on the original image and mask.
248         eroded = cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # erode
249         dilated = cv2.dilate(eroded, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # dilate
250         contours = cv2.findContours(dilated, cv2.RETR_EXTERNAL, cv2.CHAIN_APPROX_NONE)[-2] # find contour
251         area_max_contour, area_max = getAreaMaxContour(contours) # find the biggest contour
252
253         if area_max > 200: # find the biggest area
254             (centerx, centery), radius = cv2.minEnclosingCircle(area_max_contour) # Get the smallest circumscribed circle
255             msg.center_x = int(Misc.map(centerx, 0, size_m[0], 0, img_w))
256             msg.center_y = int(Misc.map(centery, 0, size_m[1], 0, img_h))
257             msg.data = int(Misc.map(radius, 0, size_m[0], 0, img_w))
258             cv2.circle(img, (msg.center_x, msg.center_y), msg.data+5, range_rgb[color], 2)
259             publish_en = True
260
261     if publish_en:
262         if (time.time()-pub_time) >= 0.06:
263             result_pub.publish(msg) # publish result
264             pub_time = time.time()

```

4.1.1 Binarization

Use the `inRange()` function in the `cv2` library to binarize the image

```

246 frame_mask = cv2.inRange(frame_lab, tuple(color_range['min']), tuple(color_range['max']))
    # Bitwise operation operates on the original image and mask.

```

The first parameter “`frame_lab`” is the input image.

The second parameter “`tuple(color_range['min'])`” is the lower limit of threshold.

The third parameter “`tuple(color_range['max'])`” is the upper lower of threshold.

4.1.2 Dilation and Erosion

To lower interference and make image smoother, the image needs to be dilated and eroded.

```

247 eroded = cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # erode
248 dilated = cv2.dilate(eroded, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # dilate

```

`erode()` function is applied to erode image. Take code “`eroded =`

`cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (3, 3)))`” as

example. The meaning of parameters in parentheses are as follow:

The first parameter “frame_mask” is the input image.

The second parameter “cv2.getStructuringElement(cv2.MORPH_RECT, (3, 3))” is the structural elements and kernel that determines the nature of operation. The first parameter in parentheses is the shape of kernel and the second parameter is the size of kernel.

dilate() function is applied to dilate image. The meaning of parameters in parentheses is the same as the parameters of erode() function.

4.1.3 Obtain the contour of the maximum area

After processing the above image, obtain the contour of the recognition target. The findContours() function in cv2 library is involved in this process.

```
249 contours = cv2.findContours(dilated, cv2.RETR_EXTERNAL, cv2.CHAIN_APPROX_NONE)[-2]  
    # find contour
```

The erode() function is applied to erode. Take code “contours = cv2.findContours(dilated, cv2.RETR_EXTERNAL, cv2.CHAIN_APPROX_NONE)[-2]” as example.

The first parameter “dilated” is the input image.

The second parameter “cv2.RETR_EXTERNAL” is the contour retrieval mode.

The third parameter “cv2.CHAIN_APPROX_NONE)[-2]” is the approximate method of contour.

Find the maximum contour from the obtained contours. To avoid interference, set a minimum value. Only when the area is greater than this minimum value, the target contour will take effect. The minimum value here is “50”.

```
250 area_max_contour, area_max = getAreaMaxContour(contours) # find the biggest contour  
251  
252 if area_max > 200: # find the biggest area
```


4.1.4 Obtain Position Information

The `minAreaRect()` function in `cv2` library is used to obtain the minimum external rectangle of the target contour, and the coordinates of its four vertices are obtained through the `boxPoints()` function. Then, the coordinates of the center point of the rectangle can be calculated from the coordinates of the vertexes of the rectangle.

```

253 (centerx, centery), radius = cv2.minEnclosingCircle(area_max_contour)
    # Get the smallest circumscribed circle
254 msg.center_x = int(Misc.map(centerx, 0, size_m[0], 0, img_w))
255 msg.center_y = int(Misc.map(centery, 0, size_m[1], 0, img_h))
256 msg.data = int(Misc.map(radius, 0, size_m[0], 0, img_w))
257 cv2.circle(img, (msg.center_x, msg.center_y), msg.data+5, range_rgb[color], 2)
258 publish_en = True

```

4.2 Control Action

Control the servos by calling `bus_servo_control.set_servos()` function.

```

114 # robotic arm x-axis tracking
115 if abs(center_x - img_w/2.0) < 15:
116     center_x = img_w/2.0
117     arm_x_pid.SetPoint = img_w/2.0 # set
118     arm_x_pid.update(center_x) # current
119     arm_x += arm_x_pid.output # output
120     arm_x = 200 if arm_x < 200 else arm_x
121     arm_x = 800 if arm_x > 800 else arm_x
122
123 # robotic arm y-axis tracking
124 if abs(center_y - img_h/2.0) < 15:
125     center_y = img_h/2.0
126     arm_y_pid.SetPoint = img_h/2.0 # set
127     arm_y_pid.update(center_y) # current
128     arm_y += arm_y_pid.output # output
129     arm_y = 50 if arm_y < 50 else arm_y
130     arm_y = 300 if arm_y > 300 else arm_y
131
132 # robotic arm movement
133 bus_servo_control.set_servos(joints_pub, 20, ((3, arm_y), (6, arm_x)))

```

Servo control takes “`bus_servo_control.set_servos(joints_pub, 20, ((3, arm_y), (6, arm_x)))`” as example and the meaning of parameters in parentheses are as follow:

The first parameter “`joints_pub`” is to publish the message of the servo control node.

The second parameter “20” is the running time.

The third parameter is “(3, arm_y), (6, arm_x)”. “3” is the servo number, “arm_y” is the servo angle.

```
135         # chassis car x-axis tracking
136         if abs(arm_x - Arm_X) < 5:
137             arm_x = Arm_X
138             x_pid.SetPoint = Arm_X # set
139             x_pid.update(arm_x)    # current
140             dx = x_pid.output      # output
141             dx = -200 if dx < -200 else dx
142             dx = 200 if dx > 200 else dx
143
144         # chassis car y-axis tracking
145         if abs(arm_y - Arm_Y) < 5:
146             arm_y = Arm_Y
147             y_pid.SetPoint = Arm_Y # set
148             y_pid.update(arm_y)    # current
149             dy = -y_pid.output     # output
150             dy = -180 if dy < -180 else dy
151             dy = 180 if dy > 180 else dy
152
153         # chassis car movement
154         set_translation.publish(dx,dy)
155         move = True
```

Motor control takes the code “set_translation.publish(dx,dy)” as example and the meaning of parameters in parentheses are as follow:

The first parameter “dx” is the movement distance of car in x-axis.

The second parameter “dy” is the movement distance of car in y-axis.