

Lesson 2 Color Tracking

1. Working Principle

Recognize the color and process it with Lab color space. Firstly, convert RGB color space to LAB and then perform binaryzation, dilation and erosion and other operations to obtain the outline of the target color. Then frame the contour of the color to complete color recognition.

Then process height of robotic arm after recognition. The coordinates (x,y,z) of center point of image take as the set value and the currently obtained coordinates are used as input value to update pid.

Then, calculate on the basis the feedback of image position. Finally, the coordinate value will change linearly through the change of the position, so as to achieve the effect of tracking.

The source code of program is located in:

`/home/ubuntu/armpi_pro/src/color_tracking/scripts/color_tracking_node.py`

```

98 def run(msg):
99     global x_dis, y_dis, z_dis
100
101     center_x = msg.center_x
102     center_y = msg.center_y
103     radius = msg.data
104
105     with lock:
106         if __isRunning and target_color != 'None':
107             if radius > 20:
108                 # x-axis tracking
109                 x_pid.SetPoint = img_w / 2.0 # Set
110                 x_pid.update(center_x) # Current
111                 dx = x_pid.output # Output
112                 x_dis += int(dx)
113                 # limiting
114                 x_dis = 200 if x_dis < 200 else x_dis
115                 x_dis = 800 if x_dis > 800 else x_dis
116
117                 # The y-axis positive direction tracking
118                 if radius - RADIUS < -3:
119                     y1_pid.SetPoint = RADIUS # Set
120                     y1_pid.update(radius) # Current
121                     dy = y1_pid.output # Output
122
123                 # The y-axis negative direction tracking
124                 elif radius - RADIUS > 5:
125                     y2_pid.SetPoint = RADIUS # Set
126                     y2_pid.update(radius) # Current
127                     dy = y2_pid.output # Output
128                 else:
129                     dy = 0
130                 y_dis += dy
131                 y_dis = 0.12 if y_dis < 0.12 else y_dis
132                 y_dis = 0.25 if y_dis > 0.25 else y_dis



```

2. Operation Steps

i It should be case sensitive when entering command and the “Tab” key can be used to complete the keywords.

2.1 Enter Game

1) Turn on ArmPi Pro and connect to the system desktop via No Machine.

2) Click  and select  in pop-up interface to open the terminal.

3) Enter command “rosservice call /color_tracking/enter “{}” and press “Enter”

to enter this game. After entering, the prompt will be printed, as the figure shown below:

```
ubuntu@ubuntu:~$ rosservice call /color_tracking/enter "{}"  
success: True  
message: "enter"
```

2.2 Start image transmission

2.2.1 Start with browser

To avoid consuming too much running memory of Raspberry Pi. It is recommended to use an external browser to open the transmitted image.


The specific steps are as follows:

- 1) Select a browser. Take Google Chrome as example.



- 2) Then enter the default IP address "192.168.149.1:8080/" (Note: this IP address is the default IP address for direction connection mode. If it is LAN mode, please enter "Device IP address: 8080/" for example, "192.168.149.1:8080/")
If fail to open, you can try it several times or restart camera.

Note: If it is in LAN mode, the method to obtain device IP address can refer to "10.Advanced Lesson"/ 1.Network Configuration Lesson/ LAN Mode Connection.



- 3) Then, click the option shown in the following figure to open the display window of the transmitted image.

Available ROS Image Topics:

- [/lab_config_manager/image_result \(Snapshot\)](#)
- [/visual_processing/image_result \(Snapshot\)](#)

/visual_processing/image_result




2.2.2 Start with rqt

1) After completing the steps of “2.1 Enter Game” and do not exit the terminal, open a new terminal.

2) Enter command “rqt_image_view” and press “Enter” to open rqt.

```
ubuntu@ubuntu:~$ rqt_image_view
```

3) Click the red box as the figure shown below, select “/visual_processing/image_result” for the topic of color tracking and remain other settings unchanged.



Note: After opening image, the topic option must be selected. Otherwise, after starting game, the recognition process can not be displayed normally.

2.3 Start Game

1) Now, enter the terminal according to the steps in “2.1 Enter Game” and input command “rosservice call /color_tracking/set_running "data: true"”. Then if the prompt shown in the following red box appears, which means game has been started successfully.

```
ubuntu@ubuntu:~$ rosservice call /color_tracking/set_running "data: true"
success: True
message: "set_running"
```

4) After starting the game, select the target color. Take blue as example.
Enter command “rosservice call /color_tracking/set_target "data: 'blue'”.

Note: If want to change to green or red, you can fill in green or red in "data: ' ' ' (The entered command should be case sensitive).

```
ubuntu@ubuntu:~$ roscall /color_tracking/set_target "data: 'blue'"
success: True
message: "set_target"
ubuntu@ubuntu:~$
```

2.4 Stop and Exit

1) If want to stop the game, enter command “roscall /visual_patrol/set_running "data: false"”. After stopping, you can refer to the content of “2.3 Start Game” to change the tracking color to green or red.

```
ubuntu@ubuntu:~$ roscall /color_tracking/set_running "data: false"
success: True
message: "set_running"
ubuntu@ubuntu:~$
```

2) If want to exit the game, enter command “roscall /color_tracking/exit "{}” to exit.


```
ubuntu@ubuntu:~$ roscall /color_tracking/exit "{}"
success: True
message: "exit"
ubuntu@ubuntu:~$
```

Note: Before exiting the game, it will keep running when Raspberry Pi is powered on. To avoid consume too much running memory of Raspberry Pi, you need to exit the game first according to the operation steps above before performing other AI vision games.

3) If want exit the image transmission, press “Ctrl+C” to return and open the terminal of rqt. If fail to exit, please keep trying several times.

3. Project Outcome

After starting game, place the blue block within the detected range of camera. The target color will be framed in rqt tool after recognition. At this time, move the block slowly. Then the robotic arm will move with the target color.



4. Function Extension


4.1 Add New Recognition Color

Color tracking has three built-in color red, green and blue. In addition to the built-in colors, we can add other recognition colors. For example, add pink as a new recognizable color. The operation steps are as follow:

1) Open the terminal, enter command “python3 lab_config/main.py” and press “Enter” to open the tool for color threshold adjustment. If no transmitted image appears in the pop-up interface, it means the camera fails to connect and needs to be checked whether the wire is connected.


```
ubuntu@ubuntu:~$ python3 lab_config/main.py
libEGL warning: DRI2: failed to authenticate
```


2) After the camera is connected completely, we can see that the right side is real-time transmitted image and the right side is the color to be collected. Then click “Add” in the lower right color to name the new color.




3) Fill in the name of added color and click “Ok”. The color will be updated to “pink” in the color options bar in the lower right corner.






4) Point the camera at the pink object. Then drag the following six slider bars until the pink area becomes white and other areas become black and click “Save” to save data.




5) Find the source code of color tracking

`/home/ubuntu/armipi_pro/src/color_tracking/scripts/` and double click to open.




6) Then input the RGB value of pink "pink': (203, 192, 255)," in source code and save it.



7) Open the terminal and enter command "sudo systemctl restart start_node.service" to restart the game. (Wait for 1 minute to hear "Di" sound, then the game is restarted successfully)

8) Refer to the operation steps from 2.1 Enter game to 2.3 Start game to start color tracking.

9) Put pink object in front of the camera then slowly move the object. Arm Pi Pro will move with the pink object.



10) If want to add other colors as new recognizable color, you can refer to the operation steps of “4.1 Add New Color”.

5. Program Parameter Instruction

5.1 Image Process

The source code of image process program is located in:

`/home/ubuntu/armpi_pro/src/visual_processing/scripts/visual_processing_node.py`

```

272 def colors_detect(img, color_list):
273     global pub_time
274     global publish_en
275     global color_range_list
276
277     if color_list == 'RGB' or color_list == 'rgb':
278         color_list = ('red','green','blue')
279     else:
280         return img
281
282     msg = Result()
283     msg.data = 0
284     color_num = 0
285     max_area = 0
286     color_area_max = None
287     areaMaxContour_max = 0
288
289     img_copy = img.copy()
290     img_h, img_w = img.shape[:2]
291     frame_resize = cv2.resize(img_copy, size_m, interpolation=cv2.INTER_NEAREST)
292     frame_lab = cv2.cvtColor(frame_resize, cv2.COLOR_BGR2LAB) # convert image into LAB space
293
294     for color in color_list:
295         if color in color_range_list:
296             color_range = color_range_list[color]
297             frame_mask = cv2.inRange(frame_lab, tuple(color_range['min']), tuple(color_range['max'])) # Bitwise operation
298             # operates on the original image and mask.
299             eroded = cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # erode
300             dilated = cv2.dilate(eroded, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # dilate
301             contours = cv2.findContours(dilated, cv2.RETR_EXTERNAL, cv2.CHAIN_APPROX_NONE)[-2] # find contour
302             areaMaxContour, area_max = getAreaMaxContour(contours) # find the biggest contour

```

5.1.1 Binarization

Use the `inRange ()` function in the `cv2` library to binarize the image

```

246 frame_mask = cv2.inRange(frame_lab, tuple(color_range['min']), tuple(color_range['max']))
    # Bitwise operation operates on the original image and mask.

```

The first parameter “`frame_lab`” is the input image.

The second parameter “`tuple(color_range['min'])`” is the lower limit of threshold.

The third parameter “`tuple(color_range['max'])`” is the upper lower of threshold.

5.1.2 Dilation and Erosion

To lower interference and make image smoother, the image needs to be dilated and eroded.

```

247 eroded = cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # erode
248 dilated = cv2.dilate(eroded, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # dilate

```

`erode()` function is applied to erode image. Take code “`eroded = cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2)))`” as example. The meaning of parameters in parentheses are as follow:

The first parameter “`frame_mask`” is the input image.

The second parameter “cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))” is the structural elements and kernel that determines the nature of operation. The first parameter in parentheses is the shape of kernel and the second parameter is the size of kernel.

dilate() function is applied to dilate image. The meaning of parameters in parentheses is the same as the parameters of erode() function.

5.1.3 Obtain the contour of the maximum area

After processing the above image, obtain the contour of the recognition target. The findContours() function in cv2 library is involved in this process.

```
249 contours = cv2.findContours(dilated, cv2.RETR_EXTERNAL, cv2.CHAIN_APPROX_NONE)[-2]  
# find contour
```

The erode() function is applied to erode. Take code “contours = cv2.findContours(dilated, cv2.RETR_EXTERNAL, cv2.CHAIN_APPROX_NONE)[-2]” as example.

The first parameter “dilated” is the input image.

The second parameter “cv2.RETR_EXTERNAL” is the contour retrieval mode.

The third parameter “cv2.CHAIN_APPROX_NONE)[-2]” is the approximate method of contour.

```
250 area_max_contour, area_max = getAreaMaxContour(contours) # find the biggest contour  
251  
252 if area_max > 200: # find the biggest area
```

5.1.4 Obtain Position Information

The minAreaRect() function in cv2 library is used to obtain the minimum exterior rectangle of the target contour, and the coordinates of its four vertices are obtained through the boxPoints() function. Then, the coordinates of the center point of the rectangle can be calculated from the coordinates of the vertexes of the rectangle.

```

253 (centerx, centery), radius = cv2.minEnclosingCircle(area_max_contour) # Get the smallest circuncircle
254 msg.center_x = int(Misc.map(centerx, 0, size_m[0], 0, img_w))
255 msg.center_y = int(Misc.map(centery, 0, size_m[1], 0, img_h))
256 msg.data = int(Misc.map(radius, 0, size_m[0], 0, img_w))
257 cv2.circle(img, (msg.center_x, msg.center_y), msg.data+5, range_rgb[color], 2)
258 publish_en = True

```

5.2 Control Tracking

Take the X and Y coordinates of the center point of image as the set values, and take the X and Y coordinates of the currently recognized target as the input values for inverse kinematic calculation to obtain the target position.

```

134 # z-axis tracking
135 z_pid.SetPoint = img_h / 2.0 # Set
136 z_pid.update(center_y) # Current
137 dy = z_pid.output # Output
138 z_dis += dy
139
140 z_dis = 0.22 if z_dis > 0.22 else z_dis
141 z_dis = 0.17 if z_dis < 0.17 else z_dis
142
143 target = ik.setPitchRanges((0, round(y_dis, 4), round(z_dis, 4)), -90, -85, -95) # 逆运动学求解
144 if target:
145 # Publish servo control node message to control the movement of robotic arm
146 servo_data = target[1]
147 bus_servo_control.set_servos(joints_pub, 20, (
148 (3, servo_data['servo3']), (4, servo_data['servo4']), (5, servo_data['servo5']), (6, x_dis)))

```

A the code of inverse kinematic calculation “ik.setPitchRanges((0, round(y_dis, 4), round(z_dis, 4)), -90, -85, -95)” as example. The meaning of parameters in parentheses are as follow:

The first parameter “0” is the value of x-axis, “round(y_dis, 4)” is the value of y-axis and “round(z_dis, 4)” is the value of z-axis.

The second parameter “-90” is the pitch angle.

The third parameter “-85” is the range of the pitch angle.

The fourth parameter “-95” is

Servo control takes the code “bus_servo_control.set_servos(joints_pub, 20, ((3, servo_data['servo3']), (4, servo_data['servo4']), (5, servo_data['servo5']), (6, x_dis)))” as example. The meaning of parameters in parentheses are as follow:

The first parameter “joints_pub” is to publish the message of servo control node.

The second parameter “20” is the running time.

The third parameter is “((3, servo_data['servo3']), (4, servo_data['servo4']), (5, servo_data['servo5']), (6, x_dis)”. Among them, “3” is the servo number, “servo_data['servo3']” is the servo angle and the remaining parameters are the same.