Lesson 1 Intelligent Picking

1. Working Principle

Firstly, recognize the color and convert the object color through Lab color.

Then, frame the target object with circle after processing the object image.

After recognizing, robotic arm will pick according to the position of block and place it to the specified position.

The source code of program is located in: /home/ubuntu/armpi pro/src/intelligent grasp/scripts/intelligent grasp node.py

```
lock = RLock()
     ik = ik_transform.ArmIK()
32
    set_visual = 'line'
33
    detect_step = 'color' # 步骤: 巡线或者检测色块
34
35
    line_color = 'yellow' # 巡线颜色
    stable = False
                   #色块夹取判断变量
37
     place_en = False #色块放置判断变量
    position_en = False #色块夹取前定位判断变量
38
39
      __isRunning = False # 玩法控制开关变量
    block clamp = False #搬运色块标记变量
40
41
    chassis_move = False # 底盘移动标记变量
42
43
    x_{dis} = 500
44
    y_{dis} = 0.15
45
     line_width = 0
46
     line_center_x = 0
47
    line_center_y = 0
48
    color_centreX = 320
    color_centreY = 410
49
50
    color_center_x = 0
51
    color_center_y = 0
52
    detect color = 'None'
53
    target_color = 'None'
54
55
    img_h, img_w = 480, 640
56
57
    line x pid = PID.PID(P=0.002, I=0.001, D=0) # pid初始化
    color_x_pid = PID.PID(P=0.06, I=0, D=0)
58
59
    color_y_pid = PID.PID(P=0.00003, I=0, D=0)
60
61
    □range_rgb = {
62
        'red': (0, 0, 255),
       'blue': (255, 0, 0),
63
64
        'green': (0, 255, 0),
65
       'black': (0, 0, 0),
66
       'yellow': (0, 255, 255),
       'white': (255, 255, 255),
```

2. Operation Steps

It should be case sensitive when entering command and the "Tab" key can be used to complete the keywords.

2.1 Enter Game

- 1) Turn on ArmPi Pro and connect to the system desktop via No Machine.
- 2) Click and select Terminal Emulator in pop-up interface to open the terminal.
- 3) Enter command "rosrun intelligent_grasp intelligent_grasp_node.py" and press "Enter" to run the program of intelligent picking.

```
Terminal - ubuntu@ubuntu: ~

File Edit View Terminal Tabs Help

ubuntu@ubuntu: ~$ rosrun intelligent_grasp intelligent_grasp_node.py

[DEBUG] [1656323672.081631]: init_node, name[/intelligent_grasp], pid[29207]

[DEBUG] [1656323672.087030]: binding to 0.0.0.0 0

[DEBUG] [1656323672.092958]: bound to 0.0.0.0 40927

[DEBUG] [1656323672.099349]: ... service URL is rosrpc://ubuntu:40927

[DEBUG] [1656323672.106312]: [/intelligent_grasp/get_loggers]: new Service instance

[DEBUG] [1656323672.119004]: ... service URL is rosrpc://ubuntu:40927

[DEBUG] [1656323672.123501]: [/intelligent_grasp/set_logger_level]: new Service instance

[DEBUG] [1656323672.156584]: ... service URL is rosrpc://ubuntu:40927

[DEBUG] [1656323672.194220]: ... service URL is rosrpc://ubuntu:40927

[DEBUG] [1656323672.205671]: [/intelligent_grasp/exit]: new Service instance

[DEBUG] [1656323672.238603]: ... service URL is rosrpc://ubuntu:40927

[DEBUG] [1656323672.238603]: ... service URL is rosrpc://ubuntu:40927

[DEBUG] [1656323672.238603]: ... service URL is rosrpc://ubuntu:40927

[DEBUG] [1656323672.251362]: [/intelligent_grasp/set_running]: new Service instance

[DEBUG] [1656323672.264174]: ... service URL is rosrpc://ubuntu:40927

[DEBUG] [1656323672.278885]: [/intelligent_grasp/heartbeat]: new Service instance

[DEBUG] [1656323672.278885]: [/intelligent_grasp/heartbeat]: new Service instance

[DEBUG] [1656323672.815466]: node[/intelligent_grasp/heartbeat]: new Service instance

[DEBUG] [1656323672.815466]: node[/intelligent_grasp/heartbeat]: new Service instance

[DEBUG] [1656323672.815466]: node[/intelligent_grasp/heartbeat]: new Service instance
```

4) Do not close the opened terminal and open a new terminal. Then enter command "rosservice call /intelligent_grasp/enter "{}"" to enter and press "Enter" to enter this game. After entering, the terminal will print the prompt as the figure shown below:

```
Terminal - ubuntu@ubuntu: ~

File Edit View Terminal Tabs Help

ubuntu@ubuntu: ~ * rosservice call /intelligent_grasp/enter "{}"

success: True
message: "enter"

ubuntu@ubuntu: ~ *
```

2.2 Start image transmission

2.2.1 Start with browser

To avoid consuming too much running memory of Raspberry Pi. It is recommended to use an external browser to open the transmitted image.


The specific steps are as follows:

1) Select a browser. Take Google Chrome as example.



2) Then enter the default IP address "192.168.149.1:8080/" (Note: this IP address is the default IP address for direction connection mode. If it is LAN mode, please enter "Device IP address+: 8080/" for example, "192.168.149.1:8080/") If fail to open, you can try it several times or restart camera.

Note: If it is in LAN mode, the method to obtain device IP address can refer to "10.Advanced Lesson"/ 1.Network Configuration Lesson/ LAN Mode Connection.



3) Then, click the option shown in the following figure to open the display window of the transmitted image.



Available ROS Image Topics:

(lah config manager/image result (Snanshot) /visual_processing/image_result (Snapshot)




2.2.2 Start with rqt

- 1) After completing the steps of "2.1 Enter Game" and do not exit the terminal, open a new terminal.
- 2) Enter command "rqt_image_view" and press "Enter" to open rqt.

ubuntu@ubuntu:~\$ rqt_image_view

3) Click the red box as the figure shown below, select "/visual_processing/image_result" for the topic of line following and remain other settings unchanged.

4



Note: After opening image, the topic option must be selected. Otherwise, after starting game, the recognition process can not be displayed normally.

2.3 Start Game

Now, enter the terminal according to the steps in "2.1 Enter Game" and input command "rosservice call /visual_patrol/set_running "data: true"". Then if the prompt shown in the following red box appears, which means game has been started successfully.

```
ubuntu@ubuntu:~$ rosservice call /intelligent_grasp/set_running "data: true"
success: Irue
message: "set_running"
```

2.4 Stop and Exit

1) If want to stop the game, enter command "rosservice call /intelligent_grasp/set_running" to exit.

2) If want to exit the game, enter command "rosservice call /intelligent_grasp/exit "\{\}"" to exit.

```
ubuntu@ubuntu:~$ rosservice call /intelligent_grasp/exit "{}"
success: True
message: "exit"
```

3) To avoid consume too much running memory of Raspberry Pi, after exiting the game and returning to the terminal of running game programmings, press "Ctrl+C" to exit the program. If fail to exit, please keep trying several times.

Note: Before exiting the game, it will keep running when Raspberry Pi is powered on. To avoid consume too much running memory of Raspberry Pi, you need to exit the game first according to the operation steps above before performing other Al vision games.


4) If want to close the image transmission, press "Ctrl+C" to return and open the terminal of rqt. If fail to exit, please keep trying several times.



3. Project Outcome

After starting the game, the robotic arm will Rotate to search the block. We can see that that target block is framed in rqt tool after recognition. Then the robotic arm will slowly move to the block, grip and place it to the specified position.





4. Program Parameter Instruction

4.1 Image Process

The source code of image process program is located in:

 $/home/ubuntu/armpi_pro/src/visual_processing/scripts/visual_processing_node.py$

```
def colors_detect(img, color_list):
273
274
275
                            global pub_time
                            global publish_en
                            global color_range_list
276
277
                            if color_list == 'RGB' or color_list == 'rgb':
278
279
280
281
                                  color_list = ('red', 'green', 'blue')
                            else:
                                  return ima
282
                           msg = Result()
 283
                           msg.data = 0
284
285
286
                            color_num = 0
                           max_area = 0
                           color area max = None
 287
                           areaMaxContour_max = 0
 288
289
290
291
                            img_copy = img.copy()
                            img_h, img_w = img.shape[:2]
                           frame_resize = cv2.resize(img_copy, size_m, interpolation=cv2.INTER_NEAREST) frame_lab = cv2.cvtColor(frame_resize, cv2.COLOR_BGR2LAB) # convert image into LAB space
 292
 293
294
295
296
297
                            for color in color_list:
                                  if color in color_range_list:
                                         color_range = color_range_list[color]
frame_mask = cv2.inRange(frame_lab, tuple(color_range['min']), tuple(color_range['max'])) # Bitwise operation
                                         operates on the original image and mask
 298
                                         eroded = cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2)))
299
300
                                         dilated = cv2.dilate(eroded, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2)))
                                                                                                                                                                                                                                                                                                  # dilate
                                         contours = cv2.find Contours (dilated, cv2.RETR\_EXTERNAL, cv2.CHAIN\_APPROX\_NONE) \cite{Contours} + find contours (dilated, cv2.RETR\_EXTERNAL, cv2.RETR\_EXTERNAL
 301
                                         areaMaxContour, area_max = getAreaMaxContour(contours)
                                                                                                                                                                                                                                                                       # find the biggest contour
 302
                                         if areaMaxContour is not None:
 303
                                               if area_max > max_area:#find the biggest area
 304
                                                      max_area = area_max
 305
                                                       color_area_max = color
 306
                                                       areaMaxContour_max = areaMaxContour
```

4.1.1Binarization

Use the inRange () function in the cv2 library to binarize the image

```
frame_mask = cv2.inRange(frame_lab, tuple(color_range['min']), tuple(color_range['max']))

# Bitwise operation operates on the original image and mask.
```

The first parameter "frame lab" is the input image.

The second parameter "tuple(color range['min'])" is the lower limit of threshold.

The third parameter "tuple(color_range['max'])" is the upper lower of threshold.

4.1.2 Dilation and Erosion

To lower interference and make image smoother, the image needs to be dilated and eroded.

```
eroded = cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # erode dilated = cv2.dilate(eroded, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))) # dilate
```

erode() function is applied to erode image. Take code "eroded =
cv2.erode(frame_mask, cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2)))" as
example. The meaning of parameters in parentheses are as follow:



The first parameter "frame_mask" is the input image.

The second parameter "cv2.getStructuringElement(cv2.MORPH_RECT, (2, 2))" is the structural elements and kernel that determines the nature of operation. The first parameter in parentheses is the shape of kernel and the second parameter is the size of kernel.

dilate() function is applied to dilate image. The meaning of parameters in parentheses is the same as the parameters of erode() function.

4.1.3 Obtain the contour of the maximum area

After processing the above image, obtain the contour of the recognition target. The findContours() function in cv2 library is involved in this process.

```
contours = cv2.findContours(dilated, cv2.RETR_EXTERNAL, cv2.CHAIN_APPROX_NONE)[-2]
# find contour
```

The erode() function is applied to erode. Take code "contours = cv2.findContours(dilated, cv2.RETR_EXTERNAL, cv2.CHAIN_APPROX_NONE)[-2]" as example.

The first parameter "dilated" is the input image.

The second parameter "cv2.RETR_EXTERNAL" is the contour retrieval mode.

The third parameter "cv2.CHAIN_APPROX_NONE)[-2]" is the approximate method of contour.

Find the maximum contour from the obtained contours. To avoid interference, set a minimum value. Only when the area is greater than this minimum value, the target contour will take effect. The minimum value here is "50".

```
areaMaxContour, area_max = getAreaMaxContour(contours) # find the biggest contour if areaMaxContour is not None:
if area_max > max_area:#find the biggest area
```

4.1.4 Obtain Position Information

The minAreaRect() function in cv2 library is used to obtain the minimum

9

external rectangle of the target contour, and the coordinates of its four vertices are obtained through the boxPoints() function. Then, the coordinates of the center point of the rectangle can be calculated from the coordinates of the vertexes of the rectangle.

```
(centerx, centery), radius = cv2.minEnclosingCircle(areaMaxContour_max) # Get the smallest circumcircle msg.center_x = int(Misc.map(centerx, 0, size_m[0], 0, img_w))
msg.center_y = int(Misc.map(centery, 0, size_m[1], 0, img_h))
radius = int(Misc.map(radius, 0, size_m[0], 0, img_w))
rect = cv2.minAreaRect(areaMaxContour_max) #Minimum circumscribed rectangle
box = np.int0(cv2.boxPoints(rect)) #The four vertices of the smallest circumscribed rectangle
msg.angle = int(math.degrees(math.atan2(box[1][1] - box[0][1], box[1][0] - box[0][0])))

cv2.circle(img, (msg.center_x, msg.center_y), radius+5, range_rgb[color_area_max], 2)
```

Determine the color block with the largest area.

```
if color_area_max == 'red': #the maximum color area is red
msg.data = 1
elif color_area_max == 'green': #the maximum color area is green
msg.data = 2
elif color_area_max == 'blue': #the maximum color area is blue
msg.data = 3
```

4.2 Control Action

The position of the target on x, y and z axes are obtained after processing image. Then get the target position calculated by inverse kinematics and grip it.

```
while __isRunning:
            if arm_move and detect_color != 'None': # wait for grasping
              target_color = detect_color # save the target color
115
               set_rgb(target_color) # set RGB light color
116
117
118
119
120
               rospy.sleep(0.1)
               buzzer_pub.publish(0.1) # The buzzer sounds once
               bus_servo_control.set_servos(joints_pub, 500, ((1, 120),)) #open gripper
               rospy.sleep(0.5)
               target = ik.setPitchRanges((0, round(y_dis + offset_y, 4), -0.08), -180, -180, 0) #the robotic arm moves downward.
121
               if target:
                 servo_data = target[1]
123
124
                 bus_servo_control.set_servos(joints_pub, 1000, ((3, servo_data['servo3']), (4, servo_data['servo4']),
                                                 (5, servo_data['servo5']), (6, x_dis)))
125
               rospy.sleep(1.5)
               bus_servo_control.set_servos(joints_pub, 500, ((1, 450),)) # close gripper
               rospy.sleep(0.8)
```

The inverse kinematics takes "ik.setPitchRanges((0, round(y_dis + offset_y, 4), -0.08), -180, -180, 0)" as example and the meaning of parameters in parentheses are as follow:

The first parameter is "(0, round(y dis + offset y, 4)". "0" is the position of the target



on x-axis. "round(y_dis, 4)" is the position of the target on y-axis. "round(z_dis, 4)" is the position of the target on z-axis.

The second parameter "-180" is the angle of x-axis.

The third parameter "-180" is the range of the pitch angle.

The fourth parameter "0" is the range of pitch angle.

The servo control takes the code "bus_servo_control.set_servos(joints_pub, 20, ((3, servo_data['servo3']), (4, servo_data['servo4']), (5, servo_data['servo5']), (6, x_dis)))" as example and the meaning of parameters in parentheses is as follow:

The first parameter "joints_pub" is to publish the message of servo control node.

The second parameter "20" is the running time.

The third parameter is "((3, servo_data['servo3']), (4, servo_data['servo4']), (5, servo_data['servo5']), (6, x_dis)". Among them, "3" is the servo number. "servo_data['servo3']" and the rest of parameters are the servo angle.

11